

Appendix 12-1 Table of Output Fields of Discrepancy Information (Delivered after Departure Time Registration (ATD))

Field No. (*1)	Field Name	Category (*2)	Output Code (*3)	Particulars
2	Vessel Code	M	Distinctive letter (call sign)	Distinctive letter (call signs) of vessel is output.
3	Voyage Number	C		The Voyage Number is output.
4	Carrier Code	M		The Code for NACCS (*) is output. * The code is given by the NACCS Center to the shipping company.
5	Port of Loading Code	C	Port Code (Refer to UN/LOCODE in Operation Codes (including Country Code.))	The Port of Loading Code is output in The Port Code (UN/LOCODE 5 digits)
6	Port of Loading Suffix	C		The Port of Loading Branch Number is output.
7	Date of Departure (from port)	C		Actual Date of Departure is output in the western calendar format (8 digits)
8	Time of Departure (from port)	C		Actual Time of Departure is output in time (4 digits).
9	Time Difference from Greenwich Mean Time	C		(1)The subtraction between the local time and GMT is output in hour(s) and minute(s)(4 digits) with a plus or minus sign "+" or "-." (2) If Actual Date of Departure and Actual Time of Departure are entered in GMT, "00000" is output.
10	Relaxed Application Area Identifier	C		If the vessel departs from a port in an area where the deadline for filing is relaxed, "Y" is output.
11	Port of Discharge Code	C	Port Code (Refer to UN/LOCODE in Operation Codes (including Country Code.))	Not output.
12	Port of Discharge Suffix	C		Not output.
13	Date of Arrival (at port)	C		Not output.
14	Overflow Identifier	C		(1) If the number of B/L to be output exceeds 100, "Y" is output. (2) If "Y" is output, check through integrated maintenance and logistics (IML) because some B/Ls are not output.
* Fields [15] through [21] below can be repeatedly entered up to 100 times.				
15	B/L Number	M		(1) B/L numbers are output in ascending order. (2) Only B/L numbers deemed to deviate are output.
16	Discrepancy Identifier (no House B/L)	C		If no House B/L is registered for Master B/L, "H" is output.
17	Discrepancy Identifier (no Master B/L)	C		If no Advance Cargo Information Registration (AMR) is conducted for Master B/L linked to House B/L, "M" is output.
18	Discrepancy	C		If the vessel information differs between Master B/L and

Field No. (* 1)	Field Name	Category (* 2)	Output Code (* 3)	Particulars
	Identifier (Discrepancy in Vessel Information)			House B/L, which are linked, "S" is output.
19	Discrepancy Identifier (Overdue Reporting)	C		If the deadline for filing is overdue, "T" is output.
20	Discrepancy Identifier (Incomplete Advance Filing)	C		Not output.
21	Discrepancy Identifier (Incomplete Departure Time Registration)	C		Not output.

(* 1) Field numbers of Operation Specifications (output fields) for operations.

Operation Specifications are in the Advance Filing Rules web site (<http://www.naccscenter.com/afr/>).

(* 2) The following shows how to read "Category."

(1)

Category	Particulars
M	Must
C	Conditional field
F	Musts after complementary
X	No entry is available.
-	Ignore the entry.

(2) "Category" level

(Ex.)

Field Name	Category	
Field A	C	
Field B		M

Lower level Fields are under the category of upper level fields.

* Field A is a conditional field, which is sometimes but not always entered.

Field B is compulsory at a level lower than Field A. If Field A is entered, Field B must be entered.

(* 3) Operation Codes are in the Advance Filing Rules web site (<http://www.naccscenter.com/afr/>).

Appendix 12-2 Table of Output Fields of Discrepancy Information (Delivered after Manifest Submission (DMF))

Field No. (* 1)	Field Name	Category (* 2)	Output Code (* 3)	Particulars
2	Vessel Code	M	Distinctive letter (call sign)	Distinctive letter (call sign) of vessels is output.
3	Voyage Number	C		Voyage Number is output only when the field is entered in the Manifest Information Registration (MFR).
4	Carrier Code	M		The Carrier Code for NACCS (*) is output. * The code is given by the NACCS Center to the shipping company.
5	Port of Loading Code	C	The Port Code (Refer to UN/LOCODE in Operation Codes (including Country Code.))	Not output.
6	The Port of Loading Suffix	C		Not output.
7	Date of Departure (from port)	C		Not output.
8	Time of Departure (from port)	C		Not output.
9	Time Difference from Greenwich Mean Time	C		Not output.
10	Relaxed Application Area Identifier	C		Not output.
11	Port of Discharge Code	C	The Port Code (Refer to UN/LOCODE in Operation Codes (including Country Code.))	The Port of Unloading Code is output in UN/LOCODE (5 digits).
12	Port of Discharge Suffix	C		The Port of Unloading Branch Number is output.
13	Date of Arrival (at port)	C		The Date of Arrival is output.
14	Overflow Identifier	C		(1) If the number of B/L to be output exceeds 100, "Y" is output. (2) If "Y" is output, check through IML or Inquiry about Manifest Status (IMI).
* Fields [15] through [21] below can be repeatedly entered up to 100 times.				
15	B/L Number	M		(1) B/L numbers are output in ascending order. (2) Only B/L numbers deemed to deviate are output.
16	Discrepancy Identifier (no House B/L)	C		Not output.
17	Discrepancy Identifier (no Master B/L)	C		Not output.
18	Discrepancy Identifier (Discrepancy in Vessel Information)	C		Not output.
19	Discrepancy Identifier (Overdue Reporting)	C		Not output.
20	Discrepancy Identifier (Incomplete Advance Filing)	C		If AMR is not conducted, "A" is output.
21	Discrepancy Identifier (Incomplete Departure Time Registration)	C		If ATD is not conducted, "D" is output.

(* 1) Field numbers of Operation Specifications (output fields) for operations.

Operation Specifications are in the Advance Filing Rules web site (<http://www.naccscenter.com/afr/>).

(* 2) The following shows how to read "Category."

(1)

Category	Particulars
M	Must
C	Conditional field
F	Musts after complementary
X	No entry is available
-	Ignore the entry

(2) "Category" level

(Ex.)

Field Name	Category	
Field A	C	
Field B		M

Lower level fields are under the category of upper level fields.

* Field A is a conditional field, which is sometimes but not always entered.

Field B is compulsory at a level lower than Field A. If Field A is entered, Field B must be entered.

(* 3) Operation Codes are in the Advance Filing Rules web site (<http://www.naccscenter.com/afr/>).