

Appendix 8 Table of Input Fields of Advance Cargo Information Registration (AMR) (after the update of NACCS in Oct. 2017)

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
2	Function Type Code	M		1		Enter "9."
3	SP Code	C		16		No entry is required. * Those who run service provider business operations send a Service Provider Code and password to NACCS.
6	Vessel Code	M		9	Distinctive letter (call sign)	(1) Enter the vessel's distinctive letter (call sign). (2) Enter it in the left-aligned format. (3) 9999 cannot be entered. NB. IMO number is different from call sign and not acceptable for the Vessel Code.
7	Laden Vessel Name	F		35		(1) If the Vessel Code (call sign) entered in "Item No. 6" is registered in NACCS, no entry is required. (2) If the Vessel Code (call sign) entered in "Item No. 6" is not registered in NACCS, a Vessel Name must be entered.
8	Nationality Code of Vessel	F		2	Country/Region Code (Refer to UN/LOCODE in Operation Code)	(1) If the Vessel Code (call sign) entered in "Field No. 6" is registered in NACCS, no entry is required. (2) If the Vessel Code (call sign) entered in "Field No. 6" is not registered in NACCS, a Country Code (2-digit Country Code of UN/LOCODE (hereinafter the same.)) must be entered for the vessel nationality.
9	Operating Carrier Voyage Number	C		10		(1) Enter the Voyage Number of the carrier which actually operates the vessel whose Vessel Code entered in "Field 6". (2) Enter it in the left-aligned format.
10	Voyage Number	M		10		(1) Enter the Voyage Number of each carrier using the ship. (2) Enter it in the left-aligned format.
11	Carrier Code	M		4	Carrier Code for NACCS	Enter the Carrier Code for NACCS (*) in units of the carrier using the ship. * The code is registered in NACCS as a Carrier Code.
12	Port of Loading Code	M		5	Port Code (Refer to UN/LOCODE in Operation Codes.)	(1) For a port where container cargo is loaded onto a vessel intended for entry into a port in Japan, enter the Port Code (UN/LOCODE 5 digits (hereinafter the same.)). In case of transshipment, enter the port where cargo is firstly shipped for Japan (port of origin) in "Field No. 26." (2) If the Port Code is not registered in NACCS, enter a code with "ZZZ" after the Country/Region Code (2 digits).
13	Name of Port of Loading	F		20		(1) If the port of loading code entered in "Field No. 12" is registered in NACCS,

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						<p>no entry is required.</p> <p>(2) If the lower 3 digits of Port of Loading Code entered in "Field No. 12" are "ZZZ," the Port of Loading Name must be entered.</p>
14	Port of Loading Suffix		C	1		<p>(1) If a vessel does not make more than one port call in a single voyage, it need not enter the Branch Number.</p> <p>(2) If a vessel makes more than one port call in a single voyage, enter the Branch Number.</p> <p>(Example of entries)</p> <ul style="list-style-type: none"> - If the port call at the same port is the second one in the same voyage, enter "1," and if the tenth one, "9." <p>NB. Be careful not to enter a Branch Number which does not match the number of port calls, since the Departure Time Registration (ATD) in later phase has to be done per each Port of Loading Suffix.</p>
15	B/L Number		M	35		<p>Follow the entry method below and enter the B/L number.</p> <p>(Entry Method)</p> <p>1) 1st through 4th digits Enter the Carrier Code for NACCS.</p> <p>2) From 5th digit Enter the Ocean (Master) B/L number. (NB. If the Carrier Code for NACCS is used at the beginning of B/L number in the issued bill of lading, the 1) above is unnecessary.)</p> <p>NB.</p> <ul style="list-style-type: none"> - The B/L number entered in this "Field No. 15" has to be adequately notified to the relevant economic operators, since this number has to be related to the filing of House B/L information and the filing of Master (Ocean) B/L information under the Manifest Submission. - If changes in Ocean (Master) B/L number entered in this "Field No. 15" happen, such as separations, combines or switches, due to the revision of transport contract, etc., it is necessary 1) to carry out the Advance Cargo Information Registration (AMR) or the Update Registered Advance Cargo Information (CMR) with the revised B/L number after the changes, then 2) to relate the original B/L information and the revised B/L information via the Association of Registered B/L Numbers (BLL).

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
16	Estimated Date of Departure	M		8		Enter the western calendar format (8 digits: yyyyymmdd) for the Scheduled Date of Departure from the port of loading at local time or Greenwich mean time (GMT).
17	Estimated Time of Departure	M		4		Enter the time (4 digit: hhmm) of the Estimated Time of Departure from the port of loading at local time or Greenwich mean time (GMT).
18	Time Difference from Greenwich Mean Time	M		5		<p>(1) If the Estimated Date of Departure in "Field No. 16" and the Estimated Time of Departure (from the port of loading) in "Field No. 17" are entered at local time, enter the time difference between the local time and Greenwich mean time (GMT) in hour(s) and minute (s) (4 digits) with a plus or minus sign "+" or "-."</p> <p>(2) If the port of loading is "THBKK" and the estimated local time of departure is "20:02"(Greenwich mean time is "13:02"), entry examples are as follows.</p> <p>1) If the estimated time of departure is entered in GMT Field No.17: "1302" Field No.18: "00000"</p> <p>2) If the estimated time of departure is entered in local time Field No.17: "2002" Field No.18: "+0700"</p>
19	Relaxed Application Area Identifier	C		1		In case of short-distance shipping routes which are subject to relaxed application in accordance with the Rules on Enforcement of the Customs Law (*), enter "Y." * Refer to the main document 3-(3)-B and Appendix 2.
20	Master B/L Identifier	C		1		If a related House B/L exists for the B/L number in "Field No. 15,"enter "M."
* [21] fields can be repeatedly entered up to three times.						
21	Notification Forwarding Party Code	C		5	User Code (*) * The code is provided by the NACCS Center in entering into an agreement for use to identify a user. Note that it differs from the Reporter ID in 4-(3) of the main document. (Hereinafter the same shall apply in this document.)	<p>(1) If a filer has related other users such as a NACCS user in Japan conduction following procedures and the related other users may have to conduct the "Inquiry About Advance Cargo Information Registration (IAR)", enter the user code of such user.</p> <p>(2) If the related other users above have to receive an advance notice of risk analysis results from Japan Customs, enter the user code of such user.</p>
22	Port of Discharge	M		5	Port Code	(1) Enter the Port Code (UN/LOCODE 5

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
	Code				(Refer to UN/LOCODE in Operation Codes)	<p>digits) for a port where container cargo is unloaded (in case of a temporary landing, a port where cargo is temporary landing).</p> <p>(2) If the Port Code (UN/LOCODE 5 digits) is not registered in NACCS, enter a code with "ZZZ" after the Country Code (2 digits). (This also entails that the last three digits of Port of Discharge Code are automatically converted to "ZZZ" when a Port Code that is not registered in NACCS is entered.)</p> <p>NB.</p> <ul style="list-style-type: none"> - With regard to a Port Code in Japan, enter the codes registered in NACCS for ocean-going ships. - If the cargo for registration is transit cargo, enter a Port Code out of Japan.
23	Port of Discharge Suffix	C		1		<p>(1) If a vessel does not make more than one port call in a single voyage, it need not enter the Branch Number.</p> <p>(2) If a vessel makes more than one port call in a single voyage, enter the Branch Number.</p> <p>(Example of entries)</p> <ul style="list-style-type: none"> - If the port call at the same port is the second one in the same voyage, enter "1," and if the tenth one, "9." <p>NB. Be careful not to enter a Branch Number which does not match the number of port calls, since the Filing of the Manifest Submission (DMF) in later phase has to be done per each Port of Loading Suffix.</p>
24	Estimated Date of Arrival	M		8		<p>(1) Enter the Estimated Date of Arrival (at the port of discharge) in the western calendar format (8 digits: yyyyymmdd)</p> <p>(2) Enter the time in Japanese Standard Time (JST).</p>
25	Container Operator Code	C		5	User Code	<p>(1) If cargo is carried in a container yard after it is unloaded in Japan, enter the user code of a container operation company.</p> <p>(2) If the container operation company does not obtain any user code, enter "99999."</p> <p>(3) This is must element in order to conduct Manifest Submission (DMF) without conducting Manifest Information Registration (MFR). Hence, if this method is planned to be employed and the Container Operator Code is unknown at the timing of AMR, the Container Operator Code must be entered by the Update Registered Advance Cargo Information (CMR)</p>

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						before the execution of the DMF.
26	Port of Origin code	M		5	Port Code (Refer to UN/LOCODE in Operation Codes)	(1) Enter the Port Code (UN/LOCODE 5 digits) for the Port of Origin of container cargo. In case of transshipment, enter the port where cargo is firstly shipped for Japan (port of origin). (2) If the Port Code (UN/LOCODE 5 digits) is not registered in NACCS, enter a code with "ZZZ" after the Country/Region Code (2 digits). NB. It must be noted that the last three digits of Port of Origin Code are automatically converted to "ZZZ" when a port code that is not registered in NACCS is entered.
27	Port of Origin Name	F		20		(1) If the Port of Origin Code entered in "Field No. 26" is registered in NACCS, no entry is required. (2) If "ZZZ" is entered in the lower 3 digits of the Port Code entered in "Field No. 26," which entails that the last three digits of Port of Origin Code are automatically converted to "ZZZ" when a port code that is not registered in NACCS is entered, the Port of Origin Name must be entered.
28	Place of Delivery Code	M		5	City Code (Refer to UN/LOCODE in Operation Codes)	(1) Enter the City Code (UN/LOCODE 5 digits) for the Place of Delivery of the container cargo. In the case of temporary landing cargo, it is not the same as the port of discharge code entered in "Field No. 22" (2) If the City Code (5 digits) is not registered in NACCS, enter the code with "ZZZ" after the Country/Region Code (2 digits). NB. It must be noted that the three letters from the third digits are automatically converted to "ZZZ" when a city code that is not registered in NACCS is entered.)
29	Place of Delivery Name	F		20		(1) If the delivery place entered in "Field No. 28" is registered in NACCS, no entry is required. (2) If "ZZZ" is entered in the lower 3 digits of the Place of Delivery Code entered in "Field No. 28," which entails that the last three digits of Place of Delivery Code are automatically converted to "ZZZ" when a city code that is not registered in NACCS is entered, the delivery place must be entered.
30	Final Destination Code	C		5	City Code (Refer to UN/LOCODE in Operation Codes)	(1) Enter the City Code (UN/LOCODE 5 digits) for the final destination of container cargo.

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						(2) If the City Code (5 digits) is not registered in NACCS, enter the code with "ZZZ" after the Country Code (2 digits). NB. It must be noted that the three letters from the third digits are automatically converted to "ZZZ" when a city code that is not registered in NACCS is entered.)
31	Final Destination Name		F	20		(1) If the Final Destination Name entered in "Field No. 30" is registered in NACCS, no entry is required. (2) If "ZZZ" is entered in the lower 3 digits of the final destination code entered in "Field No. 30," which entails that the last three digits of Final Destination Code are automatically converted to "ZZZ" when a city code that is not registered in NACCS is entered, the Final Destination Name must be entered.
32	Consignor Code		C	17	Importer Exporter Code (*) * The code provided by Japan Customs or the Japan Association for Simplification of International Trade Procedures (JASTPRO) to identify importers/exporters. Corporate Number (*) * This is provided by National Tax Agency of Japan to identify corporates.	(1) In case of a consignor with an Importer Exporter Code or a Corporate Number, enter the Importer Exporter Code. (2) In case of a consignor without any Importer Exporter Code or a Corporate Number, no entry is required.
33	Consignor Name		F	70		(1) If a Consignor Code is entered in "Field No. 32," except that if a Corporate Number that is not related to an Importer Exporter Code (hereinafter referred to as "unrelated Corporate Number") is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 32," a Consignor Name must be entered. NB. In principal, the consignor who actually ships the cargo must be entered. However, if "M" is entered in "Field No. 20", it is allowed to enter the name of NVOCC at the consignor side.
34	Consignor Address (block entry)		C	175		(1) If a Consignor Code is entered in "Field No. 32," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						in "Field No. 32", and if Consignor Address" 1/4 (Street and number/P.O. box) of "Field No. 35" through Consignor Address 3/4 (city name) of "Field No. 37" are not entered, entry of this "Field No. 34" is required.
35	Consignor Address 1/4 (Street and number/P.O. box)	c		70		(1) If a Consignor Code is entered in "Field No. 32," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 32," and if a Consignor Address (block entry) is not entered in "Field No. 34", the Consignor's Address 1/4 (Street and number/P.O. box) must be entered in this "Field 35."
36	Consignor Address 2/4 (Street and number/P.O. box)	c		35		(1) If a Consignor Code is entered in "Field No. 32," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 32," and if a Consignor Address (block entry) is not entered in "Field No. 34", the Consignor's Address 2/4 (Street and number/P.O. box) must be entered in this "Field 36."
37	Consignor Address 3/4 (City name)	c		35		(1) If a Consignor Code is entered in "Field No. 32," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 32," and if a Consignor Address (block entry) is not entered in "Field No. 34", Consignor's Address 3/4 (City name) must be entered in this "Filed No. 37."
38	Consignor Address 4/4 (Country sub-entity, name)	c		35		(1) If a Consignor Code is entered in "Field No. 32," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 32," and if a Consignor Address (block entry) is not entered in "Field No. 34", enter Consignor's Address 4/4 (Country sub-entity, name) in this "Field No. 38" as needed.
39	Consignor Postal Code (Postcode identification)	c		9		(1) If a Consignor Code is entered in "Field No. 32," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						unrelated Corporate Number is entered in "Field No. 32," enter Consignor Postcode (Postcode identification). (Do not enter any space and/nor delimiter.) (3) If there is no postcode in the country/region where consignor is located, no entry is required.
40	Consignor Country Code (Country, coded)	F		2	Country/Region Code (Refer to UN/LOCODE in Operation Codes)	(1) If a Consignor Code is entered in "Field No. 32," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 32", a country/region code (2 digits) where the consignor is located must be entered. (3) "ZX", "ZY", "ZZ" cannot be entered.
41	Consignor Telephone Number	F		14		(1) If a Consignor Code is entered in "Field No. 32," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 32", a telephone number of the consignor shown in "Field No.33" must be entered. NB. As for the telephone number, enter from a long distance code, which means the entry of a national code is not necessary. (Enter numbers only. Do not enter any space and/nor delimiter.)
42	Consignee Code	C		17	Importer Exporter Code (*) * The code provided by Japan Customs or the Japan Association for Simplification of International Trade Procedures (JASTPRO) to identify importers/exporters. Corporate Number (*) * This is provided by National Tax Agency of Japan to identify corporates.	(1) In case of the consignee with an Importer Exporter Code or a Corporate Number, enter the Importer Exporter Code or the Corporate Number. (2) In case of the consignee without any Importer Exporter Code or Corporate Number, no entry is required.
43	Consignee Name	F		70		(1) If a Consignee Code is entered in "Field No. 42," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is entered or an unrelated Corporate Number is entered in "Field No. 42," a Consignee Name must be entered. NB. - If "TO ORDER" is entered in this "Field No. 43", exact name, address and

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						<p>telephone number must be entered in from Notify Party Code in "Field No. 52" to Notify Party Telephone Number in "Field No. 61".</p> <p>- In principal, the consignee who actually imports the cargo must be entered. However, if "M" is entered in "Field No. 20", it is allowed to enter the NVOCC at the consignee's side.</p>
44	Consignee Address (block entry)		C	175		<p>(1) If a Consignee Code is entered in "Field No. 42," except that an unrelated Corporate Number is entered, no entry is required.</p> <p>(2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 42", and if the Consignee Address 1/4 (Street and number/P.O. box) in "Field No. 45" through Consignee Address 3/4 (City name) in "Field No. 45" are not entered, Consignee Address (block entry) must be entered.</p> <p>NB. If "TO ORDER" is entered in "Field No. 43", "TO ORDER" must be entered again in this "Field No. 44".</p>
45	Consignee Address 1/4 (Street and number/P.O. box)		C	70		<p>(1) If a Consignee Code is entered in "Field No. 42," except that an unrelated Corporate Number is entered, no entry is required.</p> <p>(2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 42", and if Consignee Address (block entry) in "Field No. 44" is not entered, the Consignee's Address 1/4 (Street and number/P.O. box) must be entered.</p>
46	Consignee Address 2/4 (Street and number/P.O. box)		C	35		<p>(1) If a Consignee Code is entered in "Field No. 42," except that an unrelated Corporate Number is entered, no entry is required.</p> <p>(2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 42", and if Consignee Address (block entry) in "Field No. 44" is not entered," the Consignee's Address 2/4 (Street and number/P.O. box) must be entered.</p>
47	Consignee Address 3/4 (City name)		C	35		<p>(1) If a Consignee Code is entered in "Field No. 42," except that an unrelated Corporate Number is entered, no entry is required.</p> <p>(2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 42", and if Consignee Address (block entry) in "Field No. 44" is not entered, the</p>

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						Consignee Address 3/4 (City name) must be entered.
48	Consignee Address 4/4 (Country sub-entity, name)	C		35		(1) If a Consignee Code is entered in "Field No. 42," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 42", and if Consignee Address (block entry) in "Field No. 44" is not entered, enter Consignee's Address 4/4 (Country sub-entity, name) as needed.
49	Consignee Postal Code (Postcode identification)	C		9		(1) If a Consignee Code is entered in "Field No. 42," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 42", the Consignee's Postcode (Postcode identification) must be entered. (Do not enter any space and/nor delimiter.)
50	Consignee Country Code (Country, coded)	F		2	Country/Region Code (Refer to UN/LOCODE in Operation Codes)	(1) If a Consignee Code is entered in "Field No. 42," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 42", a country/region code (2 digits) must where the consignee is located must be entered. (3) "ZX", "ZY", "ZZ" cannot be entered. NB. If "TO ORDER" is entered in "Field No. 43", a country/region code (2 digits) that is same as "Notify Party Country Code" in "Field No. 60" must be entered.
51	Consignee Telephone Number	F		14		(1) If a Consignee Code is entered in "Field No. 42," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 42", a telephone number from a long distance code of the consignee shown in "Field No.43" must be entered. NB. As for the telephone number, enter from a long distance code, which means the entry of a national code is not necessary. (Enter numbers only. Do not enter any space and/nor delimiter.). If "TO ORDER" is entered in "Field No. 43", enter the same telephone number as " Field No. 61" or enter "TO RDER".

Field No. (* 1)	Field Name	Category (* 2)	Length	Operation Code (* 3)	Particulars
		* Fields [52] Notify Party Code through [61] Notify Party Telephone Number can be repeatedly entered up to twice.			
52	Notify Party Code	C	17	<p>Importer Exporter Code (*) * The code provided by Japan Customs or the Japan Association for Simplification of International Trade Procedures (JASTPRO) to identify importers/exporters.</p> <p>Corporate Number (*) * This is provided by National Tax Agency of Japan to identify corporates.</p>	<p>(1) In case of a notify party with an Importer Exporter Code or a Corporate Number, enter the Importer Exporter Code or the Corporate Number.</p> <p>(2) In case of a notify party without any Importer Exporter Code or a Corporate Number, no entry is required.</p>
53	Notify Party Name	C	70		<p>(1) If a Notify Party Code is entered in "Field No. 52," except that an unrelated Corporate Number is entered, no entry is required.</p> <p>(2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 52," Notify Party Name must be entered.</p> <p>NB. "SAME AS CONSIGNEE" cannot be entered.</p>
54	Notify Party Address (block entry)	C	175		<p>(1) If a Notify Party Code is entered in "Field No. 52," except that an unrelated Corporate Number is entered, no entry is required.</p> <p>(2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 52," and if "Notify Party Address (block entry)" is not entered, "Notify Party Address" 1/4 (Street and number/P.O. box) in "Field No. 55" through "Notify Party Address 3/4 (City name)" in "Field No. 57" must be entered.</p>
55	Notify Party Address1/4 (Street and number/P.O. box)	C	70		<p>(1) If a Notify Party Code is entered in "Field No. 52," except that an unrelated Corporate Number is entered, no entry is required.</p> <p>(2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 52," and if "Notify Party Address (block entry)" is not entered, "Notify Party Address 1/4 (Street and number/P.O. box)" must be entered.</p>
56	Notify Party Address2/4 (Street and number/P.O. box)	C	35		<p>(1) If a Notify Party Code is entered in "Field No. 52," except that an unrelated Corporate Number is entered, no entry is required.</p> <p>(2) If a Notify Party Code is not entered or</p>

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						an unrelated Corporate Number is entered in "Field No. 52," and if "Notify Party Address (block entry)" is not entered,, "Notify Party Address 2/4 (Street and number/P.O. box)" must be entered.
57	Notify Party Address 3/4 (City name)	C		35		(1) If a Notify Party Code is entered in "Field No. 52," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 52," and if "Notify Party Address (block entry)" is not entered, "Notify Party Address 3/4 (City name)" must be entered.
58	Consignee Address 4/4 (Country sub-entity, name)	C		35		(1) If a Notify Party Code is entered in "Field No. 52," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 52," and if "Notify Party Address (block entry)" is not entered,enter "Notify Party Address 4/4 (Country sub-entity, name)" as needed.
59	Notify Party Postal Code (Postcode identification)	C		9		(1) If a Notify Party Code is entered in "Field No. 52," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 52," "Notify Party Postcode (Postcode identification)" must be entered. (Do not enter any space nor delimiter.)
60	Notify Party Country Code (Country, coded)	C		2	Country/Region Code (Refer to UN/LOCODE in Operation Codes (including the Country Code.))	(1) If a Notify Party Code is entered in "Field No. 52," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 52," a country/region name (2 digits) of the notify party must be entered. (3) "ZX", "ZY", "ZZ" cannot be entered.
61	Notify Party Telephone Number	F		14		(1) If a Notify Party Code is entered in "Field No. 52," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 52," a telephone number from a long distance code of the Notify Party shown in "Field No.53" must be entered. NB. As for the

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						telephone number, enter from a long distance code, which means the entry of a national code is not necessary. (Enter numbers only. Do not enter any space and/nor delimiter.).
62	Goods Description	M		350		(1) Enter specific and detailed description of goods so that cargo particulars can be easily identified. (2) Only numbers and marks cannot be entered.
63	Harmonized System Code	M		6	Harmonized System Code (HS code) (6-digit)	Enter representative goods in HS code (6 digits).
64	Mark and Number	M		140		Enter the Mark and Number of Cargo.
65	Number of Packages	M		8		(1) Enter the number of outer packages (2) "Zero (0)" cannot be entered. If packages cannot be counted, enter "1."
66	Number of Packages Unit Code	M		3	Codes for Types of Packages (Refer to Operation Codes)	Enter the Package Type Code as the number of packages unit code.
67	Gross Weight	M		10		(1) Enter the Total Gross Weight of cargo. (2) "Zero (0)" cannot be entered. (3) Enter within 10 digits including decimal point. Integral part :up to 7 digits Decimal part :up to 3 digits (4) If an integer portion is 7 digits, the weight unit code in "Field No. 68" should be "KGM." (5) If Total Gross Weight is not the weight unit code in "Field No. 68," enter a weight converted into the unit.
68	Weight Unit Code	M		3	Codes for Units of Measurement (Total Gross Weight and Total Volume) (Refer to Operation Codes)	Enter the weight unit in Codes for Units of Measurement (Total Gross Weight and Total Volume).
69	Net Weight	C		10		(1) Enter the Net Weight of the cargo. (2) "Zero (0)" cannot be entered. (3) Enter within 10 digits including decimal point. Integral part :up to 7 digits Decimal part :up to 3 digits (4) If an integer portion is 7 digits, the weight unit code in "Field 70" should be "KGM." (5) If the Net Weight is not the weight unit code in "Field No. 70," enter a weight converted into the unit.
70	Weight Unit Code		M	3	Codes for Units of Measurement (Total Net Weight and Total	Enter the unit of Net Weight in Codes for Units of Measurement (Total Net Weight and Total Volume).

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
					Volume) (Refer to Operation Codes)	
71	Measurement	M		10		(1) Enter a cargo volume. (2) "Zero (0)" cannot be entered. (3) Enter within 10 digits including decimal point. Integral part :up to 6 digits Decimal part :up to 3 digits (4) If the volume is not the volume code in "Field No. 72,"enter a volume converted into the unit.
72	Measurement Unit Code	M		3	Codes for Units of Measurement (Total Gross Weight and Total Volume) (Refer to Operation Codes)	Enter the volume unit in Codes for Units of Measurement (Total Gross Weight and Total Volume).
73	Country of Origin Code	C		2	Country/Region Code (Refer to UN/LOCODE in Operation Codes)	Enter the Country/Region Code (2 digits) for the country of origin of the cargo.
74	Special Cargo Code	C		3	SPC Code (Refer to Operation Codes)	If a special cargo is loaded, enter Special Cargo Code for the type of special cargo.
* Fields [75] IMDF Class through [76] UN No. can be repeatedly entered up to five times.						
75	IMDG Class	C		4	IMDG Code (Refer to Dangerous master (IMDG) of Operation Codes)	(1) If a dangerous cargo is loaded, enter a hazard category (class) in the International Maritime Dangerous Goods Code (IMDG code). (2) Enter the IMDG class corresponded to UN No in "Field No. 76".
76	UN No.		M	4	IMDG Code (Refer to Dangerous master (IMDG) of Operation Codes)	(1) Enter the UN No. pursuant to United Nations Recommendations on the Transport of Dangerous Goods. (2) Enter a number from "0000" to "9999." (3) In case of loading dangerous goods which are applicable to several "UN No", enter one of the "UN No".
77	Freight	C		18		(1) Enter cargo freight. (2) When entering a Freight Currency Code other than "JPY" in "Field No. 78," entries can be made up to the second decimal place. (3) When "JPY" is entered in Freight Currency Code in "Field No. 78", figures after the decimal point cannot be entered.
78	Freight Currency Code		M	3	Currency Code (Refer to Operation Codes)	Enter the Currency Code to show a currency type of freight.
79	Value	C		18		(1) If customs transit takes place after a temporary landing in Japan, the cargo values must be entered.

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						(2) When entering a value currency code other than "JPY" in "Field No. 80," entries can be made up to the second decimal place. (3) When "JPY" is entered in Value Currency Code in "Field No. 80", figures after the decimal point cannot be entered.
80	Value Currency Code		M	3	Currency Code (Refer to Operation Codes)	Enter the Currency Code for a currency type of value.
81	General Customs Transit Approval Number	C		11		If individual customs transit associated with a general customs transit approval is conducted after unloading in Japan, enter a general customs transit approval number.
82	Temporary Landing Identifier	C		3		Enter "28" in case of temporary landing cargo.
83	Reason for Temporary Landing Code		M	3	Reason for Temporary Landing Code (Refer to Operation Codes)	(1) In case of temporary landing cargo, enter a temporary landing cause code according to the following. - TRT: transshipping cargo to other outbound vessel (aircraft)(involving transportation) - TRS: transshipping cargo to other outbound vessel (aircraft)(involving no transportation) - POS: shifting cargo within the same vessel - REV: repacking goods into other containers (2) The registration of customs transit information for temporary landing cargo is not "TRS" nor "POS".
84	Duration of Temporary Landing		M	2		(1) In case of temporary landing cargo, enter the length of the temporary landing period in days, using the discharge start time and date as the initial date of reckoning. (2) "Zero (0)" cannot be entered.
85	Estimated Start Date of Transportation		C	8		(1) In case of customs transit of temporary landing cargo, enter the western calendar format (8 digits) for the start date of the transportation period. (2) Enter the time in Japanese Standard Time (JST).
86	Estimated Finish Date of Transportation		C	8		(1) In case of customs transit of temporary landing cargo, enter the western calendar format (8 digits) for the end date of the transportation period. (2) Enter the time in Japanese Standard Time (JST).
87	Code of Transportation Mode of Separate Transit/Customs	C		2		(1) In conducting customs transit of temporary landing cargo, enter codes according to the following categories:

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars														
	Transit of Temporary Landing Cargo					(2) In conducting individual customs transit associated with a comprehensive customs transit approval, enter codes according to the following categories: <table border="1"> <thead> <tr> <th>Category</th> <th>Code</th> </tr> </thead> <tbody> <tr> <td>AIRCRAFT</td> <td>6</td> </tr> <tr> <td>SHIP</td> <td>11</td> </tr> <tr> <td>BARGE</td> <td>16</td> </tr> <tr> <td>RAIL EXPRESS</td> <td>25</td> </tr> <tr> <td>TRUCK</td> <td>31</td> </tr> <tr> <td>OTHER</td> <td>17</td> </tr> </tbody> </table>	Category	Code	AIRCRAFT	6	SHIP	11	BARGE	16	RAIL EXPRESS	25	TRUCK	31	OTHER	17
Category	Code																			
AIRCRAFT	6																			
SHIP	11																			
BARGE	16																			
RAIL EXPRESS	25																			
TRUCK	31																			
OTHER	17																			
88	Arrival Place Code	C		5	Bonded Area Code (Refer to Operation Codes)	In conducting the individual customs transit associated with a comprehensive customs transit approval or customs transit of temporary landing cargo, enter the Bond Area Code for a destination.														
89	Arrival Place Name	C		35		(1) If Destination Code is entered in "Field No. 88," no entry is available. (2) If Destination Code in "Field No. 88" is not entered or an entered destination code is not registered in NACCS, the Destination Name must be entered.														
		* [90] field "Code of Other Relevant Laws and Ordinances" can be repeatedly entered up to five times.																		
90	Code of Other Relevant Laws and Ordinances	C		2	Code of Other Relevant Laws and Ordinances (Refer to Operation Codes)	In conducting individual customs transit associated with comprehensive customs transit approval or customs transit of temporary landing cargo and laws other than Customs-related are applied to cargo, enter the code associated with the law.														
91	Remark	C		140		Enter cargo information as required.														
92	Reference Number for Internal Use	C		20		Enter any number, etc. provided by your own company.														
		* Fields [93] "Container Number" through [102] "Automatic Search for Discharged Container Exclusion Identifier" can be repeatedly entered up to 200 times.																		
93	Container Number	M		12		Enter the Container Number in the left-aligned format.														
		* [94] Field "Seal Number" can be repeatedly entered up to six times per one "Container Number" in "Field No. 93".																		
94	Seal Number		M	15		(1) Enter Seal Number of container in the left-aligned format. (2) If there is no seal, enter "NO SEAL" in the 1st field.														
95	Empty/Full Container Identification		M	3		Enter "5" (full).														
96	Container Size Code		M	2		Enter the Container Size Code for the container size. This code is composed of the Container length code and the Container height code. 1st digit: Container length code(code: length [ft]) <table border="1"> <thead> <tr> <th>Category</th> <th>Code</th> </tr> </thead> <tbody> </tbody> </table>	Category	Code												
Category	Code																			

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars																										
						<table border="1"> <tr><td>10'</td><td>1</td></tr> <tr><td>20'</td><td>2</td></tr> <tr><td>40'</td><td>4</td></tr> <tr><td>Others length.</td><td>9</td></tr> </table> <p>2nd digit: Container height code(code: height [ft]''[inch]'')</p> <table border="1"> <thead> <tr><th>Category</th><th>Code</th></tr> </thead> <tbody> <tr><td>8'</td><td>0</td></tr> <tr><td>8'6"</td><td>2</td></tr> <tr><td>9'</td><td>4</td></tr> <tr><td>9'6"</td><td>5</td></tr> <tr><td>> 9'6"</td><td>6</td></tr> <tr><td>4'3"</td><td>8</td></tr> <tr><td>≤4'</td><td>9</td></tr> <tr><td>other heights</td><td>9</td></tr> </tbody> </table>	10'	1	20'	2	40'	4	Others length.	9	Category	Code	8'	0	8'6"	2	9'	4	9'6"	5	> 9'6"	6	4'3"	8	≤4'	9	other heights	9
10'	1																															
20'	2																															
40'	4																															
Others length.	9																															
Category	Code																															
8'	0																															
8'6"	2																															
9'	4																															
9'6"	5																															
> 9'6"	6																															
4'3"	8																															
≤4'	9																															
other heights	9																															
97	Container Type Code		M	2		<p>Enter the Container Type Code for the container format (type) according to the following categories:</p> <table border="1"> <thead> <tr><th>Category</th><th>Code</th></tr> </thead> <tbody> <tr><td>Dry container</td><td>GP</td></tr> <tr><td>Reefer container</td><td>RT</td></tr> <tr><td>Open top container</td><td>UT</td></tr> <tr><td>Flat rack container</td><td>PF</td></tr> <tr><td>Platform container</td><td>PL</td></tr> <tr><td>Tank container</td><td>TN</td></tr> <tr><td>Others</td><td>SN</td></tr> </tbody> </table>	Category	Code	Dry container	GP	Reefer container	RT	Open top container	UT	Flat rack container	PF	Platform container	PL	Tank container	TN	Others	SN										
Category	Code																															
Dry container	GP																															
Reefer container	RT																															
Open top container	UT																															
Flat rack container	PF																															
Platform container	PL																															
Tank container	TN																															
Others	SN																															
98	Service Type on Delivery Code		C	2		<p>(1) Enter the delivery code according to the following categories:</p> <table border="1"> <thead> <tr><th>Category</th><th>Code</th></tr> </thead> <tbody> <tr><td>Delivery in CY</td><td>51</td></tr> <tr><td>Delivery in CFS</td><td>52</td></tr> <tr><td>Delivery at the door (of consignees)</td><td>53</td></tr> </tbody> </table> <p>(2) This is must element in order to conduct Manifest Submission (DMF) without conducting Manifest Information Registration (MFR). Hence, if this method is planned to be employed and the Service Type on Delivery Code is unknown at the timing of AMR, the Container Operator Code must be entered by the Update Registered Advance Cargo Information (CMR) before the execution of the DMF.</p>	Category	Code	Delivery in CY	51	Delivery in CFS	52	Delivery at the door (of consignees)	53																		
Category	Code																															
Delivery in CY	51																															
Delivery in CFS	52																															
Delivery at the door (of consignees)	53																															
99	Container Ownership Code		M	3		<p>Enter codes for container ownership according to the following categories:</p> <table border="1"> <thead> <tr><th>Category</th><th>Code</th></tr> </thead> <tbody> <tr><td>Shipper supplied</td><td>1</td></tr> <tr><td>Carrier supplied</td><td>2</td></tr> <tr><td>Consolidator supplied</td><td>3</td></tr> <tr><td>Deconsolidator supplied</td><td>4</td></tr> <tr><td>Third party supplied</td><td>5</td></tr> </tbody> </table>	Category	Code	Shipper supplied	1	Carrier supplied	2	Consolidator supplied	3	Deconsolidator supplied	4	Third party supplied	5														
Category	Code																															
Shipper supplied	1																															
Carrier supplied	2																															
Consolidator supplied	3																															
Deconsolidator supplied	4																															
Third party supplied	5																															

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars								
100	Vanning Type Code		c	3		<p>(1) Enter vanning codes according to the following categories:</p> <table border="1"> <thead> <tr> <th>Category</th> <th>Code</th> </tr> </thead> <tbody> <tr> <td>Carrier loads</td> <td>1</td> </tr> <tr> <td>Shipper loads</td> <td>4</td> </tr> <tr> <td>Consignee loads</td> <td>16</td> </tr> </tbody> </table> <p>(2) This is must element in order to conduct Manifest Submission (DMF) without conducting Manifest Information Registration (MFR). Hence, if this method is planned to be employed and the Vanning Type Code is unknown at the timing of AMR, Vanning Type Code must be entered by the Update Registered Advance Cargo Information (CMR) before the execution of the DMF.</p>	Category	Code	Carrier loads	1	Shipper loads	4	Consignee loads	16
Category	Code													
Carrier loads	1													
Shipper loads	4													
Consignee loads	16													
101	Customs Convention on Containers (CCC) Application Identifier		c	1		<p>(1) Enter codes according to the following categories.</p> <table border="1"> <thead> <tr> <th>Category</th> <th>Code</th> </tr> </thead> <tbody> <tr> <td>If Article 8 (Special Act for International Containers, etc.) of the Act on Special Provisions of the Customs Law, etc. Incidental to customs conventions on containers and the Convention on International Transport of Goods Under Cover of TIR Carnets (TIR Convention) (hereinafter called "Special Act for Container Conventions") is not applied to containers covered by container conventions</td> <td>1</td> </tr> <tr> <td>If Article 8 (Special Act for International Containers, etc.) of Special Act for Container Conventions is applied to containers covered by container conventions</td> <td>2</td> </tr> <tr> <td>In case containers are not covered by container conventions</td> <td>3</td> </tr> </tbody> </table> <p>(2) This is must element in order to conduct Manifest Submission (DMF) without conducting Manifest Information Registration (MFR). Hence, if this method is planned to be employed and the Customs Convention on Containers (CCC) Application Identifier is unknown at the timing of AMR, the Container Operator Code must be entered by the Update Registered Advance Cargo</p>	Category	Code	If Article 8 (Special Act for International Containers, etc.) of the Act on Special Provisions of the Customs Law, etc. Incidental to customs conventions on containers and the Convention on International Transport of Goods Under Cover of TIR Carnets (TIR Convention) (hereinafter called "Special Act for Container Conventions") is not applied to containers covered by container conventions	1	If Article 8 (Special Act for International Containers, etc.) of Special Act for Container Conventions is applied to containers covered by container conventions	2	In case containers are not covered by container conventions	3
Category	Code													
If Article 8 (Special Act for International Containers, etc.) of the Act on Special Provisions of the Customs Law, etc. Incidental to customs conventions on containers and the Convention on International Transport of Goods Under Cover of TIR Carnets (TIR Convention) (hereinafter called "Special Act for Container Conventions") is not applied to containers covered by container conventions	1													
If Article 8 (Special Act for International Containers, etc.) of Special Act for Container Conventions is applied to containers covered by container conventions	2													
In case containers are not covered by container conventions	3													

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						Information (CMR) before the execution of the DMF.
102	Automatic Search for Discharged Container Exclusion Identifier		C	1		If a discharged container list is not submitted through NACCS, enter "A."

(* 1) Field No. shows item number for corresponding Procedure Specification (input fields).

Procedure Specifications can be referred to in the Advance Filing Rules web site

<https://bbs.naccscenter.com/naccs/dfw/web/afr/index.html>

(* 2) The following shows how to read "Category."

(1)

Category	Particulars
M	Mandatory
C	Conditional
F	Mandatory if there is no complementary
X	Entry is not available.
-	Ignore

(2) "Category" level

(Ex.)

Field Name	Category	
Field A	C	
Field B		M

Lower level fields are under the category of upper level fields.

* Field A is a conditional field, which is sometimes but not always entered.

Field B is compulsory at a level lower than Field A. If Field A is entered, Field B must be entered.

(* 3) Operation Codes are in the Advance Filing Rules web site

<https://bbs.naccscenter.com/naccs/dfw/web/afr/index.html>

(* 4) "Field No. 74" and fields from "Field No. 79" to "Field No. 90" are not required for the Advance Filing Rules, but are necessary in order to conduct Manifest Submission (DMF) without conducting Manifest Information Registration (MFR).