

Appendix 10 Table of Input Fields of Advance Cargo Information Registration (House B/L) (AHR) (after the update of NACCS in Oct. 2017)

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
2	Function Type Code	M		1		Enter "9."
3	SP Code	C		16		No entry is required. * Those that run service provider business operations send the Service Provider Code and password to NACCS.
6	Vessel Code	M		9	Distinctive letter (call sign)	(1) Enter the Vessel's distinctive letter (call sign). (2) Enter it in the left-aligned format. (3) 9999 cannot be entered. NB. The Vessel Code must be same as that for the related Master B/L. Hence, it is necessary to obtain this code from carrier (shipping company).
7	Laden Vessel Name	F		35		(1) If the Vessel Code (call sign) entered in "Field No. 6" is registered in NACCS, no entry is required. (2) If the Vessel Code (call sign) entered in "Field No. 6" is not registered in NACCS, the Vessel Name must be entered.
8	Nationality Code of Vessel	F		2	Country/Region Code (Refer to UN/LOCODE in Operation Codes)	(1) If the Vessel Code (call sign) entered in "Field No. 6" is registered in NACCS, no entry is required. (2) If the Vessel Code (call sign) entered in "Field No. 6" is not registered in NACCS, Country Code (2-digit Country Code of UN/LOCODE. Hereinafter the same.) must be entered for a vessel nationality.
9	Voyage Number	M		10		Enter the Voyage Number. NB. The Voyage Number must be same as that for the related Master B/L. Hence, it is necessary to obtain this number from carrier (shipping company).
10	Carrier Code	M		4		Enter the Carrier Code for NACCS in units of carriers using the ship. NB. The Carrier Code must be same as that for the related Master B/L. Hence, it is necessary to obtain this code from carrier (shipping company).
11	Port of Loading Code	M		5	Port Code (Refer to UN/LOCODE in Operation Codes)	(1) For a port where container cargo is loaded onto a vessel intended for entry into a port in Japan, enter the Port Code (UN/LOCODE 5 digits). In case of transshipment, enter the port where cargo is firstly shipped for Japan (port of origin) in "Field No. 26." (2) If the Port Code (UN/LOCODE 5 digits) is not registered in NACCS, enter a code with "ZZZ" after the Country Code (2 digits). NB. - The Port of Loading Code must be same as that for the related Master B/L. Hence, it is necessary to obtain this code from carrier (shipping company). - It must be noted that the last three digits of Port of Loading Code are automatically converted to "ZZZ" when a port code that is not registered in NACCS is entered.
12	Name of Port of Loading	F		20		(1) If the port of loading code entered in "Field No. 11" is registered in NACCS, no entry is

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						required. (2) If the lower 3 digits of Port of Loading Code entered in "Field No. 11" are "ZZZ," which entails that the last three digits of Port of Loading Code are automatically converted to "ZZZ" when a port code that is not registered in NACCS is entered, the Port of Loading Name must be entered.
13	Port of Loading Suffix	C		1		(1) If a vessel does not make more than one port call in a single voyage, it need not enter the Branch Number. (2) If a vessel makes more than one port call in a single voyage, enter the Branch Number. (Example of entries) - If the port call at the same port is the second one in the same voyage, enter "1," and if the tenth one, "9." NB. Be careful not to enter a Branch Number which does not match the number of port calls, since the Departure Time Registration (ATD) in later phase has to be done per each Port of Loading Suffix.
14	Master B/L Number	M		35		Enter the linked Master B/L number (same as "Field No. 15" of Appendix 8) . NB. The related Master B/L number must be entered. Hence, it is necessary to obtain this number from carrier (shipping company).
15	House B/L Register Completion Identifier	C		1		When all the filing of House B/L linked to Master B/L has been completed, enter "E." NB. The entry of "E" enables following, hence this entry is necessary: - The filer can receive the notice on the completion to relate Master B/L information whose number is shown in "Field No. 14" and House B/L information registered in this AHR. - The completion of filing of House B/L information is sent to the filers of relevant Master B/L information (carrier/shipping company).
16	House B/L Number	C		35		(1) Follow the entry method below and enter the House B/L Number. (Entry Method) 1) 1st through 4th digits Enter a code for House B/L (*). * House B/L Code or NVOCC Cargo Code 2) From 5th digit Enter the House B/L Number NB. - The B/L number entered in this "Field No. 16" has to be adequately notified to the relevant economic operators, since this number has to be used for "House B/L Information Registration" (NVC01) at later stage. - If changes in House B/L number entered in this "Field No. 16" happen, such as separations, combines or switches, due to the revision of transport contract, etc., it is necessary 1) to carry out the Advance Cargo

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						Information Registration (House B/L) (AHR) with the revised B/L number after the changes, then 2) to relate the original B/L information and the revised B/L information via the Association of Registered B/L Numbers (BLL).
17	Vessel Information Change Identifier	C		1		If there is a plan to change vessels due to transshipment, etc., and the information on vessel after the transshipment, etc., is unknown, the entry of "Y" in this field enables automatically to refer to the vessel information of the relevant Master B/L after the transshipment, etc.
18	Estimated Date of Departure	C		8		Enter the western calendar format (8 digits: yyyymmdd) for the Estimated Date of Departure from the port of loading at local time or Greenwich Mean Time (GMT).
19	Estimated Time of Departure (from the port of loading)		M	4		Enter the time (4 digits: hhmm) of Estimated Time of Departure from the port of loading at local time or Greenwich Mean Time (GMT).
20	Time Difference from Greenwich Mean Time		M	5		<p>(1) If the Estimated Date of Departure in "Field No. 18" and the Estimated Time of Departure (from the port of loading) in "Field No. 19" are entered at local time, enter the time difference between the local time and Greenwich Mean Time (GMT) in hour(s) and minute(s) (4 digits) with a plus or minus sign "+" or "-."</p> <p>(2) If the port of loading is "THBKK" and the estimated local time of departure is "20:02"(Greenwich mean time is "13:02") , entry examples are as follows.</p> <p>1) If the estimated time of departure is entered in GMT Field No.19: "1302" Field No.20: "00000"</p> <p>2) If the estimated time of departure is entered in local time Field No.19: "2002" Field No.20: "+0700"</p>
21	Relaxed Application Area Identifier	C		1		<p>In case of short-distance shipping routes which are subject to relaxed application in accordance with the Rules on Enforcement of the Customs Law (*), enter "Y."</p> <p>* Refer to the main document 3-(3)-B and Appendix 2.</p>
* [22] field "Notification Forwarding Party Code" can be repeatedly entered up to three times.						
22	Notification Forwarding Party Code	C		5	User Code (*) * The code is provided by the NACCS Center in entering into an agreement for use to identify a user. Note that it differs from Reporter ID in	<p>(1) If filer has other users such as a NACCS user in Japan who conducts following procedures at later stage, it is necessary to enter the user code of such user:</p> <ul style="list-style-type: none"> - "Update Registered Advance Cargo Information (House B/L) (CHR)", - "Update Registered Vessel Information for Advance Filing (Blanket)" (CMV), - "Call up House B/L Information for

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
					4-(3) of the main document. (Hereinafter the same shall apply in this document.)	Registration (NVC11)", - "Inquiry about Advance Cargo Information Registration (IAR)". (2) If an advance notice of risk analysis results from Japan Customs needs to be sent to such users, enter the user code of such user.
23	Port of Discharge Code	M		5	Port Code (Refer to UN/LOCODE in Operation Codes)	(1) Enter the Port Code (UN/LOCODE 5 digits) for a port where container cargo is unloaded (in case of a temporary landing, a port where cargo is temporary landing). (2) If the Port Code (UN/LOCODE 5 digits) is not registered in NACCS, enter a code with "ZZZ" after the Country/Region Code (2 digits). (This also entails that the last three digits of Port of Discharge Code are automatically converted to "ZZZ" when a Port Code that is not registered in NACCS is entered.) NB. - With regard to a Port Code in Japan, enter the codes registered in NACCS for ocean-going ships. - If the cargo for registration is transit cargo, enter a Port Code out of Japan.
24	Estimated Date of Arrival (at port of discharge)	M		8		(1) Enter the Estimated Date of Arrival (at port of discharge) in the western calendar format (8 digits: yyyymmdd) (2) Enter the time in Japanese Standard Time (JST).
25	Port of Origin code	M		5	Port Code (Refer to UN/LOCODE in Operation Codes)	(1) Enter the Port Code (UN/LOCODE 5 digits) for the Port of Origin of container cargo. In case of transshipment, enter the port where the cargo is firstly shipped for Japan (port of origin). (2) If the Port Code (UN/LOCODE 5 digits) is not registered in NACCS, enter a code with "ZZZ" after the Country/Region Code (2 digits). NB. It must be noted that the last three digits of Port of Origin Code are automatically converted to "ZZZ" when a port code that is not registered in NACCS is entered.
26	Port of Origin Name	F		20		(1) If the Port of Origin Code entered in "Field No. 25" is registered in NACCS, no entry is required. (2) If "ZZZ" is entered in the lower 3 digits of the Port Code entered in "Field No. 25," which entails that the last three digits of City Code are automatically converted to "ZZZ" when a city code that is not registered in NACCS is entered, the Port of Origin Name must be entered.
27	Place of Delivery Code	M		5	City Code (Refer to UN/LOCODE in Operation Codes)	(1) Enter a City Code (UN/LOCODE 5 digits) for the Place of Delivery of container cargo. In case of a temporarily landing cargo, it is not the same as the port of discharge code entered in "Field No. 23" (2) If the City Code is not registered in NACCS, enter the code with "ZZZ" after the Country/Region Code (2 digits). NB. It must be noted that the last three digits of Place of Delivery Code e are automatically

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						converted to "ZZZ" when a city code that is not registered in NACCS is entered.
28	Place of Delivery Name	F		20		(1) If a delivery place entered in "Field No. 27" is registered in NACCS, no entry is required. (2) If "ZZZ" is entered in the lower 3 digits of the Place of Delivery Code entered in "Field No. 27," which entails that the last three digits of Place of Delivery Code are automatically converted to "ZZZ" when a port code that is not registered in NACCS is entered, the delivery place must be entered.
29	Final Destination Code	C		5	City Code (Refer to UN/LOCODE in Operation Codes)	(1) Enter the City Code (UN/LOCODE 5 digits) for the final container cargo destination. (2) If the City Code is not registered in NACCS, enter the code with "ZZZ" after the Country Code (2 digits). NB. It must be noted that the last three digits of Final Destination Code are automatically converted to "ZZZ" when a city code that is not registered in NACCS is entered.
30	Final Destination Name		F	20		(1) If the Final Destination Name entered in "Field No. 26" is registered in NACCS, no entry is required. (2) If "ZZZ" is entered in the lower 3 digits of the final destination code entered in "Field No. 26," which entails that the last three digits of Final Destination Code are automatically converted to "ZZZ" when a city code that is not registered in NACCS is entered, the Final Destination Name must be entered.
31	Consignor Code	C		17	Importer Exporter Code (*) * The code provided by Japan Customs or the Japan Association for Simplification of International Trade Procedures (JASTPRO) to identify importers/exporters. Corporate Number (*) * This is provided by National Tax Agency of Japan to identify corporates.	(1) In case of a consignor with an Importer Exporter Code or a Corporate Number, enter the Importer Exporter Code. (2) In case of a consignor without any Importer Exporter Code or a Corporate Number, no entry is required.
32	Consignor Name	F		70		(1) If a Consignor Code is entered in "Field No. 31," except that if a Corporate Number that is not related to an Importer Exporter Code (hereinafter referred to as "unrelated Corporate Number") is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 31," the Consignor Name must be entered. NB. In principal, the consignor who actually ships

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						the cargo must be entered. However, if the filing of House B/L information is about a contract of transportation between other NVOCC and a consignor and it is difficult to obtain the information on consignor, it is allowed to enter the name of said NVOCC.
33	Consignor Address (block entry)	C		175		(1) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 31," except that if a Corporate Number that is not related to an Importer Exporter Code (hereinafter referred to as "unrelated Corporate Number") is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 31", and if the Consignor Address 1/4 (Street and number/P.O. box) of "Field No. 34" through Consignor Address 3/4 (city name) of "Field No. 36" are not entered, entry of this "Filed No. 33" is required.
34	Consignor Address 1/4 (Street and number/P.O. box)	C		70		(1) If a Consignor Code is entered in "Field No. 31," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 31," and if a Consignor Address (block entry) is not entered in "Field No. 33", a Consignor Address 1/4 (Street and number/P.O. box) must be entered in this "Field No. 34."
35	Consignor Address 2/4 (Street and number/P.O. box)	C		35		(1) If a Consignor Code is entered in "Field No. 31," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 31," and if a Consignor Address (block entry) is not entered in "Field No. 33", a Consignor Address 2/4 (Street and number/P.O. box) must be entered in this "Field No. 35."
36	Consignor Address 3/4 (City name)	C		35		(1) If a Consignor Code is entered in "Field No. 31," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 31," and if a Consignor Address (block entry) is not entered in "Field No. 33", a Consignor Address 3/4 (City name) must be entered in this "Field No. 36."
37	Consignor Address 4/4 (Country sub-entity, name)	C		35		(1) If a Consignor Code is entered in "Field No. 31," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 31," and if a Consignor Address (block entry) is not entered in "Field No. 33", enter a Consignor Address 4/4 (Country sub-entity, name) in this "Field No. 37" as needed.

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
38	Consignor Postal Code (Postcode identification)	C		9		(1) If a Consignor Code is entered in "Field No. 31," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 31," a Consignor Postcode (Postcode identification) where the consignor is located must be entered. (Do not enter any space or delimiter.) (3) If there is no postcode in the country/region of consignor, no entry is required.
39	Consignor Country Code (Country, coded)	F		2	Country/Region Code (Refer to UN/LOCODE in Operation Codes)	(1) If a Consignor Code is entered in "Field No. 31," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 31," a Country/Region Code (2 digits) where the consignor is located must be entered. (3) "ZX", "ZY", "ZZ" cannot be entered.
40	Consignor Telephone Number	F		14		(1) If a Consignor Code is entered in "Field No. 31," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignor Code is not entered or an unrelated Corporate Number is entered in "Field No. 31," enter a telephone number of the consignor must be entered. NB. As for the telephone number, enter from a long distance code, which means the entry of a national code is not necessary. (Enter numbers only. Do not enter any space and/nor delimiter.)
41	Consignee Code	C		17	Importer Exporter Code (*) * The code provided by Japan Customs or the Japan Association for Simplification of International Trade Procedures (JASTPRO) to identify importers/exporters. Corporate Number (*) * This is provided by National Tax Agency of Japan to identify corporates.	(1) In case of a consignee with an Importer Exporter Code or a Corporate Number, enter the Importer Exporter Code or the Corporate Number. (2) In case of a consignee without any Importer Exporter Code or Corporate Number, no entry is required.
42	Consignee Name	F		70		(1) If the Consignee Code is entered in "Field No. 41," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is not entered or an unrelated Corporate Number is in "Field No. 41," a consignee name must be entered. NB. - If "TO ORDER" is entered in this "Field No. 42", exact name, address and telephone number must be entered in from Notify Party

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						Code in "Field No. 51" to Notify Party Telephone Number in "Field No. 60". - In principal, the consignee who actually imports the cargo must be entered. However, if the filing of House B/L information is about a contract of transportation between other NVOCC and a consignee and it is difficult to obtain the information on consignee, it is allowed to enter the name of said NVOCC.
43	Consignee Address (block entry)	C		175		(1) If the Consignee Code is entered in "Field No. 41," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 42", a Consignee Address 1/4 (Street and number/P.O. box) in "Field No. 44" through Consignee Address 3/4 (city name) in "Field No. 46" must be entered. NB. If "TO ORDER" is entered in "Field No. 42", "TO ORDER" must be entered again in this "Field No. 43".
44	Consignee Address 1/4 (Street and number/P.O. box)	C		70		(1) If the Consignee Code is entered in "Field No. 41," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 41", and if a Consignee Address (block entry) in "Field No. 43" is not entered, a Consignee Address 1/4 (Street and number/P.O. box) must be entered.
45	Consignee Address 2/4 (Street and number/P.O. box)	C		35		(1) If the Consignee Code is entered in "Field No. 41," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 41", and if a Consignee Address (block entry) in "Field No. 43" is not entered, a Consignee Address 2/4 (Street and number/P.O. box) must be entered.
46	Consignee Address 3/4 (City name)	C		35		(1) If the Consignee Code is entered in "Field No. 41," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 41", and if a Consignee Address (block entry) in "Field No. 43" is not entered, a Consignee Address 3/4 (City name) must be entered.
47	Consignee Address 4/4 (Country sub-entity, name)	C		35		(1) If a Consignee Code is entered in "Field No. 41," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 41", and if a Consignee Address (block entry) in "Field No. 43" is not entered, enter a Consignee Address 4/4 (Country sub-entity, name) as needed.
48	Consignee Postal Code (Postcode identification)	C		9		(1) If a Consignee Code is entered in "Field No. 41," except that an unrelated Corporate Number is entered, no entry is required.

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						(2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 41", a Consignee Postcode (Postcode identification) must be entered. (Do not enter any space and/or delimiter.)
49	Consignee Country Code (Country, coded)	F		2	Country/Region Code (Refer to UN/LOCODE in Operation Codes)	(1) If a Consignee Code is entered in "Field No. 41," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 41", a Country/Region Code (2 digits) where the consignee is located must be entered. (3) "ZX", "ZY", "ZZ" cannot be entered. NB. If "TO ORDER" is entered in "Field No. 42", a country/region code (2 digits) that is same as "Notify Party Country Code" in "Field No. 59" must be entered.
50	Consignee Telephone Number	F		14		(1) If the Consignee Code is entered in "Field No. 41," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Consignee Code is not entered or an unrelated Corporate Number is entered in "Field No. 41", a telephone number from a long distance code of the consignee must be entered. NB. As for the telephone number, enter from a long distance code, which means the entry of a national code is not necessary. (Enter numbers only. Do not enter any space and/nor delimiter.). If "TO ORDER" is entered in "Field No. 42", enter the same telephone number as "Field No. 60" or enter "TO RDER".
* Fields [51] "Notify Party Code" through [60] "Notify Party Telephone Number" can be repeatedly entered up to twice.						
51	Notify Party Code	C		17	Importer Exporter Code (*) * The code provided by Japan Customs or the Japan Association for Simplification of International Trade Procedures (JASTPRO) to identify importers/exporters. Corporate Number (*) * This is provided by National Tax Agency of Japan to identify corporates.	(1) In case of a notify party with an Importer Exporter Code or a Corporate Number, enter the Importer Exporter Code. (2) In case of a notify party without any Importer Exporter Code or Corporate Number, no entry is required.
52	Notify Party Name	C		70		(1) If a Notify Party Code is entered in "Field No. 51," except that an unrelated Corporate Number is entered, no entry is required. (2) If the Notify Party Code is not entered in "Field No. 48," Notify Party Name must be entered.

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
						NB. "SAME AS CONSIGNEE" cannot be entered.
53	Notify Party Address (block entry)	C		175		(1) If a Notify Party Code is entered in "Field No. 51," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 51", and if Notify Party Address 1/4 (Street and number/P.O. box) in "Field No. 54" through Notify Party Address 3/4 (City name) in "Field No. 56" are not entered, Notify Party Address (block entry) must be entered.
54	Notify Party Address 1/4 (Street and number/P.O. box)	C		70		(1) If a Notify Party Code is entered in "Field No. 51," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 51", and if Notify Party Address (block entry) in "Field No. 53" is not entered, Notify Party Address 1/4 (Street and number/P.O. box) must be entered.
55	Notify Party Address 2/4 (Street and number/P.O. box)	C		35		(1) If a Notify Party Code is entered in "Field No. 51," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 51", and if Notify Party Address (block entry) in "Field No. 53" is not entered, Notify Party Address 2/4 (Street and number/P.O. box) must be entered.
56	Notify Party Address 3/4 (City name)	C		35		(1) If a Notify Party Code is entered in "Field No. 51," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 51", and if Notify Party Address (block entry) in "Field No. 53" is not entered, Notify Party Address 3/4 (City name) must be entered.
57	Notify Party Address 4/4 (Country sub-entity, name)	C		35		(1) If a Notify Party Code is entered in "Field No. 51," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 51", and if Notify Party Address (block entry) in "Field No. 53" is not entered, enter Notify Party Address 4/4 (Country sub-entity, name) a.
58	Notify Party Postal code (Postcode identification)	C		9		(1) If a Notify Party Code is entered in "Field No. 51," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 51", Notify Party Postcode (Postcode identification) must be entered. (Do not enter any space and/or delimiter.)
59	Notify Party Country Code (Country, coded)	C		2	Country/Region Code (Refer to	(1) If a Notify Party Code is entered in "Field No. 51," except that an unrelated Corporate Number is entered, no entry is required.

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
					UN/LOCODE in Operation Codes)	(2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 51", a country/region name (2 digits) of the notify party must be entered. (3) "ZX", "ZY", "ZZ" cannot be entered.
60	Notify Party Telephone Number	F		14		(1) If a Notify Party Code is entered in "Field No. 51," except that an unrelated Corporate Number is entered, no entry is required. (2) If a Notify Party Code is not entered or an unrelated Corporate Number is entered in "Field No. 51", a telephone number of the Notify Party from a long distance code must be entered. (Do not enter any space and/or delimiter.)
61	Goods Description	M		350		(1) Enter specific and detailed description of goods so that particulars of the cargo can be easily identified. (2) Only numbers and symbols cannot be entered.
62	Harmonized System Code	M		6	Harmonized System Code (HS code) (6-digit)	Enter representative goods in HS code (6 digits).
63	Marks and Numbers	M		140		Enter the Mark and Number of Cargo.
64	Number of Packages	M		8		(1) Enter the number of outer packages (2) "Zero (0)" cannot be entered. If packages cannot be counted, enter "1."
65	Number of Packages Unit Code	M		3	Codes for Types of Packages Code (Refer to Operation Codes)	Enter the Package Type Code for the number of packages unit code.
66	Gross Weight	M		10		(1) Enter Total Gross Weight of the cargo. (2) "Zero (0)" cannot be entered. (3) Enter within 10 digits including decimal point. Integral part :up to 6 digits Decimal part :up to 3 digits (4) If Total Gross Weight is not the weight unit code in "Field No. 67," enter a weight converted into the unit.
67	Weight Unit Code	M		3	Codes for Units of Measurement (Total Gross Weight and Total Volume) (Refer to Operation Codes)	Enter the weight unit in Codes for Units of Measurement (Total Gross Weight and Total Volume).
68	Net Weight	C		10		(1) Enter Net Weight of the cargo. (2) "Zero (0)" cannot be entered. (3) Enter within 10 digits including decimal point. Integral part :up to 6 digits Decimal part :up to 3 digits (4) If Net Weight is not the weight unit code in "Field No. 69," enter a weight converted into the unit.
69	Weight Unit Code		M	3	Codes for Units of Measurement (Total Gross Net and Total Volume) (Refer to Operation Codes)	Enter the unit of Net Weight in Codes for Units of Measurement (Total Net Weight and Total Volume).

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars
70	Measurement	M		10		(1) Enter a cargo volume. (2) "Zero (0)" cannot be entered. (3) Enter within 10 digits including decimal point. Integral part :up to 6 digits Decimal part :up to 3 digits (4) If the volume is not the Volume Code in "Field No. 71,"enter a volume converted into the unit.
71	Measurement Unit Code	M		3	Codes for Units of Measurement (Total Gross Weight and Total Volume) (Refer to Operation Codes)	Enter the volume unit in Codes for Units of Measurement (Total Gross Weight and Total Volume).
72	Country of Origin Code	C		2	Country/Region Code (Refer to UN/LOCODE in Operation Codes)	Enter the Country/Region Code (2 digits) for the country of origin of the cargo.
73	Special Cargo Code	C		3	SPC Code (Refer to Operation Codes)	If a special cargo is loaded, enter Special Cargo Code for the type of special cargo.
		* Fields [74] "IMDG Class" through [75] "UN No." can be repeatedly entered up to five times.				
74	IMDG Class	C		4	IMDG Code (Refer to Dangerous master (IMDG) of Operation Codes)	(1)If a dangerous cargo is loaded, enter a hazard category (class) in the International Maritime Dangerous Goods Code (IMDG code). (2) Enter the IMDG class corresponded to UN No in "Field No. 76".
75	UN No.		M	4	IMDG Code (Refer to Dangerous master (IMDG) of Operation Codes)	(1) Enter the UN No. in United Nations Recommendations on the Transport of Dangerous Goods. (2) Enter a number from "0000" to "9999".
76	Freight	C		18		(1) Enter the cargo freight. (2) In entering a Freight Currency Code other than "JPY" in "Field No. 77," entries can be made up to the second decimal place. (3) When "JPY" is entered in Freight Currency Code in "Field No. 77", figures after the decimal point cannot be entered.
77	Freight Currency Code		M	3	Currency Code (Refer to Operation Codes)	Enter the Currency Code to show a currency type of freight.
78	Value	C		18		(1) If customs transit is conducted after a temporary landing in Japan, a cargo values must be entered. (2) In entering a value currency code other than "JPY" in "Field No. 79," entries can be made up to the second decimal place. (3) When "JPY" is entered in Value Currency Code in "Field No. 79", figures after the decimal point cannot be entered.
79	Value Currency Code		M	3	Currency Code (Refer to Operation Codes)	Enter the Currency Code for a currency type of value.
80	Temporary Landing Identifier	C		3		Enter "28" in case of temporary landing cargo.
81	Reason for Temporary		M	3	Reason for Temporary	(1) In case of temporary landing cargo, enter a temporary landing cause code according to

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars														
	Landing Code				Landing Code (Refer to Operation Codes)	the following. - TRT: transshipping cargo to other outbound vessel (aircraft)(involving transportation) - TRS: transshipping cargo to other outbound vessel (aircraft)(involving no transportation) - POS: shifting cargo within the same vessel - REV: repacking goods into other containers (2) The registration of customs transit information for temporary landing cargo is not "TRS" nor "POS".														
82	Duration of Temporary Landing		M	2		(1) In case of temporary landing cargo, enter the length of the temporary landing period in days, using the discharge start time and date as the initial date of reckoning. (2) "Zero (0)" cannot be entered.														
83	Estimated Start Date of Transportation		C	8		(1) In case of customs transit of temporary landing cargo, enter the western calendar format (8 digits) for the start date of the transportation period. (2) Enter the time in Japanese Standard Time (JST).														
84	Estimated Finish Date of Transportation		C	8		(1) In case of customs transit of temporary landing cargo, enter the western calendar format (8 digits) for the end date of the transportation period. (2) Enter the time in Japanese Standard Time (JST).														
85	Code of Transportation Mode of Customs Transit of Temporary Landing Cargo	C		2		In conducting the customs transit of temporary landing cargo, enter codes according to the following categories: <table border="1"> <thead> <tr> <th>Category</th> <th>Code</th> </tr> </thead> <tbody> <tr> <td>AIRCRAFT</td> <td>6</td> </tr> <tr> <td>SHIP</td> <td>11</td> </tr> <tr> <td>BARGE</td> <td>16</td> </tr> <tr> <td>RAIL EXPRESS</td> <td>25</td> </tr> <tr> <td>TRUCK</td> <td>31</td> </tr> <tr> <td>OTHER</td> <td>17</td> </tr> </tbody> </table>	Category	Code	AIRCRAFT	6	SHIP	11	BARGE	16	RAIL EXPRESS	25	TRUCK	31	OTHER	17
Category	Code																			
AIRCRAFT	6																			
SHIP	11																			
BARGE	16																			
RAIL EXPRESS	25																			
TRUCK	31																			
OTHER	17																			
86	Arrival Place Code	C		5	Bonded Area Code (Refer to Operation Codes)	In conducting the customs transit of temporary landing cargo, enter the Bond Area Code for a destination.														
87	Arrival Place Name	C		35		(1) If Destination Code is entered in "Field No. 86," no entry is available. (2) If Destination Code in "Field No. 86" is not entered or an entered destination code is not registered in NACCS, the Destination Name must be entered.														
* [88] field "Code of Other Relevant Laws and Ordinances" can be repeatedly entered up to five times.																				
88	Code of Other Relevant Laws and Ordinances	C		2	Code of Other Relevant Laws and Ordinances (Refer to Operation Codes)	In conducting the customs transit of temporary landing cargo and laws other than Customs related ones are applied to cargo, enter a code associated with the law.														
89	Remark	C		140		Enter cargo information as required.														
90	Reference Number for Internal Use	C		20		Enter any number, etc. provided by your own company.														
* Fields [91] "Container Number" through [96] "Container Ownership Code" can be repeatedly entered up to 200 times.																				
91	Container Number	M		12		Enter the container number in the left-aligned format.														

Field No. (* 1)	Field Name	Category (* 2)		Length	Operation Code (* 3)	Particulars																												
* [92] field "Seal Number" can be repeatedly entered up to six times per one "Container Number" in "Field No. 91."																																		
92	Seal Number		M	15		(1) Enter the seal number of the container in the left-aligned format. (2) Without any seal, enter "NO SEAL" in the 1st field.																												
93	Empty/Full Container Identification		M	3		Enter "5" (full).																												
94	Container Size Code		M	2		<p>Enter the Container Size Code for a container size. This code is composed of the Container length code and the Container height code.</p> <p>1st digit: Container length code(code: length [ft])</p> <table border="1"> <thead> <tr> <th>Category</th> <th>Code</th> </tr> </thead> <tbody> <tr> <td>10'</td> <td>1</td> </tr> <tr> <td>20'</td> <td>2</td> </tr> <tr> <td>40'</td> <td>4</td> </tr> <tr> <td>Others length.</td> <td>9</td> </tr> </tbody> </table> <p>2nd digit: Container height code(code: height [ft]'[inch])</p> <table border="1"> <thead> <tr> <th>Category</th> <th>Code</th> </tr> </thead> <tbody> <tr> <td>8'</td> <td>0</td> </tr> <tr> <td>8'6"</td> <td>2</td> </tr> <tr> <td>9'</td> <td>4</td> </tr> <tr> <td>9'6"</td> <td>5</td> </tr> <tr> <td>> 9'6"</td> <td>6</td> </tr> <tr> <td>4'3"</td> <td>8</td> </tr> <tr> <td>≤4'</td> <td>9</td> </tr> <tr> <td>other heights</td> <td>9</td> </tr> </tbody> </table>	Category	Code	10'	1	20'	2	40'	4	Others length.	9	Category	Code	8'	0	8'6"	2	9'	4	9'6"	5	> 9'6"	6	4'3"	8	≤4'	9	other heights	9
Category	Code																																	
10'	1																																	
20'	2																																	
40'	4																																	
Others length.	9																																	
Category	Code																																	
8'	0																																	
8'6"	2																																	
9'	4																																	
9'6"	5																																	
> 9'6"	6																																	
4'3"	8																																	
≤4'	9																																	
other heights	9																																	
95	Container Type Code		M	2		<p>Enter the Container Type Code for a container format (type) according to the following categories:</p> <table border="1"> <thead> <tr> <th>Category</th> <th>Code</th> </tr> </thead> <tbody> <tr> <td>Dry container</td> <td>GP</td> </tr> <tr> <td>Reefer container</td> <td>RT</td> </tr> <tr> <td>Open top container</td> <td>UT</td> </tr> <tr> <td>Flat rack container</td> <td>PF</td> </tr> <tr> <td>Platform container</td> <td>PL</td> </tr> <tr> <td>Tank container</td> <td>TN</td> </tr> <tr> <td>Others</td> <td>SN</td> </tr> </tbody> </table>	Category	Code	Dry container	GP	Reefer container	RT	Open top container	UT	Flat rack container	PF	Platform container	PL	Tank container	TN	Others	SN												
Category	Code																																	
Dry container	GP																																	
Reefer container	RT																																	
Open top container	UT																																	
Flat rack container	PF																																	
Platform container	PL																																	
Tank container	TN																																	
Others	SN																																	
96	Container Ownership Code		M	3		<p>Enter codes for container ownership according to the following categories according to the following categories:</p> <table border="1"> <thead> <tr> <th>Category</th> <th>Code</th> </tr> </thead> <tbody> <tr> <td>Shipper supplied</td> <td>1</td> </tr> <tr> <td>Carrier supplied</td> <td>2</td> </tr> <tr> <td>Consolidator supplied</td> <td>3</td> </tr> <tr> <td>Deconsolidator supplied</td> <td>4</td> </tr> <tr> <td>Third party supplied</td> <td>5</td> </tr> </tbody> </table>	Category	Code	Shipper supplied	1	Carrier supplied	2	Consolidator supplied	3	Deconsolidator supplied	4	Third party supplied	5																
Category	Code																																	
Shipper supplied	1																																	
Carrier supplied	2																																	
Consolidator supplied	3																																	
Deconsolidator supplied	4																																	
Third party supplied	5																																	

(* 1) Field No. shows item number for corresponding Procedure Specification (input fields).

Procedure Specification can be referred to in the Advance Filing Rules website:

<https://bbs.naccscenter.com/naccs/dfw/web/afr/index.html>).

(* 2) The following shows how to read "Category."

(1)

Category	Particulars
M	Mandatory
C	Conditional
F	Mandatory if there is no complementary
X	Entry is not available
-	Ignore this field

(2) "Category" level

(Ex.)

Field Name	Category	
Field A	C	
Field B		M

Lower level Fields are under the category of upper level fields.

* Field A is a conditional field, which is sometimes but not always entered.

Field B is compulsory at a level lower than Field A. If Field A is entered, Field B must be entered.

(* 3) Operation Codes are in the Advance Filing Rules web site

<https://bbs.naccscenter.com/naccs/dfw/web/afr/index.html>.

(* 4) "Field No. 73" and fields from "Field No. 78" to "Field No. 88" are not required for the Advance Filing Rules, but are necessary in order to conduct "House B/L Information Registration (NVC01)" by quoting the Advance Cargo Information (House B/L) through "Call up House B/L Information (NVC11)".