

Appendix 17 Table of Input Fields of Application for Cargo Discharge Permission (DNC)

Field No. ( <sup>*1</sup> )	Field Name	Category ( <sup>*2</sup> )		Operation Code ( <sup>*3</sup> )	Particulars
2	Function Type Code	C			<p>[If an Application for Cargo Discharge Permission (DNC11) is used] The Function Type Code entered in DNC11 is output.</p> <p>-----</p> <p>[If an Application for Cargo Discharge Permission (DNC11) is not used] Enter "9."</p>
3	Vessel Code	M		Distinctive Letter (call sign)	<p>[If DNC11 is used] The Distinctive Letter (call sign) entered in DNC11 is output.</p> <p>-----</p> <p>[If DNC11 is not used] (1) Enter the Vessel's Distinctive Letter (call sign). (2) Enter it in the left-aligned format.</p>
4	Voyage Number	M			<p>[If DNC11 is used] The Voyage Number entered in DNC11 is output.</p> <p>-----</p> <p>[If DNC11 is not used] Enter the Voyage Number.</p>
5	Carrier Code	M			<p>[If DNC11 is used] The Carrier Code entered in DNC11 (*) is output. * The code is given by the NACCS Center to a shipping company.</p> <p>-----</p> <p>[If DNC11 is not used] Enter the Carrier Code for NACCS.</p>
6	Port of Loading Code	M		Port Code (Refer to UN/LOCODE in Operation Codes (including Country Code.))	<p>[If DNC11 is used] The Port of Loading Code entered in DNC11 is output.</p> <p>-----</p> <p>[If DNC11 is not used] Enter the Port Code (UN/LOCODE 5 digits) for a port where container cargo is unloaded (in case of a temporary landing, a port where cargo is temporary landing).</p>
7	(Estimated) Date of Arrival (at the port of discharge)	M			<p>[If DNC11 is used] (1) Enter the estimated date of arrival (at the port of discharge) in the western calendar format (8 digits) (2) Enter the time in Japanese Standard Time (JST).</p> <p>-----</p> <p>[If DNC11 is not used] (1) Enter the Estimated Date of Arrival (at the port of discharge) in the western calendar format (8 digits). (2) Enter the time in Japanese Standard Time (JST).</p>
8	(Estimated) Time of Arrival (at the port of discharge)	M			<p>[If DNC11 is used] (1) Enter the Estimated Time of Arrival at the port of discharge in hour(s) and minute(s) (4 digits). (2) Enter the time in Japanese Standard Time (JST).</p> <p>-----</p> <p>[If DNC11 is not used] (1) Enter the Estimated Time of Arrival at the port of discharge in hour(s) and minute(s) (4 digits). (2) Enter the time in Japanese Standard Time (JST).</p>
9	Start Date of the	M			<p>[If DNC11 is used] (1) Enter the discharge start date in the</p>

Field No. (*1)	Field Name	Category (*2)		Operation Code (*3)	Particulars
	Discharge				western calendar format (8 digits). (2) Enter the time in Japanese Standard Time (JST). ----- [If DNC11 is not used] (1) Enter the discharge start date in the western calendar format (8 digits). (2) Enter the time in Japanese Standard Time (JST).
10	Start Time of the Discharge	C			[If DNC11 is used] (1) Enter the discharge start time in hour(s) and minute(s) (4 digits). (2) Enter the time in Japanese Standard Time (JST). ----- [If DNC11 is not used] (1) Enter the discharge start time in hour(s) and minute(s) (4 digits). (2) Enter the time in Japanese Standard Time (JST).
11	End Date of the Discharge	M			[If DNC11 is used] (1) Enter the discharge end date in the western calendar format (8 digits). (2) Enter the time in Japanese Standard Time (JST). ----- [If DNC11 is not used] (1) Enter the discharge end date in the western calendar format (8 digits). (2) Enter the time in Japanese Standard Time (JST).
12	End Time of the Discharge	C			[If DNC11 is used] (1) If Start Time of the Discharge Period in "Field No. 10" is entered, the discharge end time must be entered in hour(s) and minute(s). (2) Enter the time in Japanese Standard Time (JST). ----- [If DNC11 is not used] (1) If the Start Time of the Discharge Period in "Field No. 10" is entered, the discharge end time must be entered in hour(s) and minute(s). (2) Enter the time in Japanese Standard Time (JST).
* [13] field can be repeatedly entered up to twice.					
13	Notify Party Code	C		User Code (*) * The code is provided by the NACCS Center in entering into an agreement for use to identify a user. Note that it differs from the Reporter ID in 4-(3) of the main document.	[If DNC11 is used] If it is necessary to notify another user of duplicate information of Application for Cargo Discharge Permission and a notice of cargo discharge permission, enter the User Code of the user. ----- [If DNC11 is not used] If it is necessary to notify another user of duplicate information of Application for Cargo Discharge Permission and a notice of cargo discharge permission, enter the User Code of the user.
* Fields [14] and [15] can be repeatedly entered up to 100 times.					
14	Distinguishing Processing	C			[If DNC11 is used] If no cargo discharge permission is applied for B/L number output in "Field No. 15," enter "X" (no application). ----- [If DNC11 is not used]

Field No. (*1)	Field Name	Category (*2)		Operation Code (*3)	Particulars
					No entry is required.
15	B/L Number	M			[If DNC11 is used] A B/L number, for which an Advance Notice Code is registered by Japan Customs, is output. ----- [If DNC11 is not used] Enter the B/L number to apply for cargo discharge permission.

(\* 1) Field numbers of Operation Specifications (input fields) for operations.

Operation Specifications are in the Advance Filing Rules web site (<http://www.naccscenter.com/afr/>).

(\* 2) The following shows how to read "Category."

(1)

Category	Particulars
M	Must
C	Conditional field
F	Musts after complementary
X	No entry is available.
-	Ignore the entry.

(2) "Category" level

(Ex.)

Field Name	Category	
Field A	C	
Field B		M

Lower level fields are under the category of upper level fields.

\* Field A is a conditional field, which is sometimes but not always entered.

Field B is compulsory at a level lower than Field A. If Field A is entered, Field B must be entered.

(\* 3) Operation Codes are in the Advance Filing Rules web site (<http://www.naccscenter.com/afr/>).