Appendix 19 Table of Input Fields of Application for Cargo Discharge Permission (DNC) (after the update of NACCS in Oct. 2017)

Field No. (*1)	Field Name	Category (*2)	Length	Operation Code	Particulars	
2	Function Type Code	С	1		[If an Application for Cargo Discharge Permission (DNC11) is used] The Function Type Code entered in DNC11 is output. [If an Application for Cargo Discharge Permission (DNC11) is not used] Enter "9."	
3	Vessel Code	М	9	Distinctive Letter (call sign)	[If DNC11 is used] The Distinctive Letter (call sign) entered in DNC11 is output.  [If DNC11 is not used] Enter the Vessel's Distinctive Letter (call sign).	
4	Voyage Number	М	10		[If DNC11 is used] The Voyage Number entered in DNC11 is output. [If DNC11 is not used] Enter the Voyage Number.	
5	Carrier Code	М	4	Carrier Code for NACCS	[If DNC11 is used] The Carrier Code entered in DNC11 (*) is output.  * The code is registered in NACCS. [If DNC11 is not used] Enter the Carrier Code for NACCS.	
6	Port of Discharge Code	M	5	Port Code (Refer to UN/LOCODE in Operation Codes)	[If DNC11 is used] The Port of Discharge Code entered in DNC11 is output.  [If DNC11 is not used] Enter the Port Code (UN/LOCODE 5 digits) for a port where container cargo is unloaded (in case of a temporary landing, a port where cargo is temporary landing).	
7	(Estimated) Date of Arrival (at the port of discharge)	M	8		[If DNC11 is used] (1) Enter the estimated date of arrival (at the port of discharge) in the western calendar format (8 digits: yyyymmdd) (2) Enter the time in Japanese Standard Time (JST).  [If DNC11 is not used] (1) Enter the Estimated Date of Arrival (at the port of discharge) in the western calendar format (8 digits: yyyymmdd). (2) Enter the time in Japanese Standard Time (JST).	
8	(Estimated) Time of Arrival (at the port of discharge)	M	4		[If DNC11 is used] (1) Enter the Estimated Time of Arrival at the port of discharge in hour(s) and minute(s) (4 digits: hhmm). (2) Enter the time in Japanese Standard Time (JST). [If DNC11 is not used] (1) Enter the Estimated Time of Arrival at the port of discharge in hour(s) and minute(s) (4 digits: hhmm). (2) Enter the time in Japanese Standard Time (JST).	

Field No. (*1)	Field Name	Category (*2)	Length	Operation Code	Particulars
9	Start Date of the Discharge	М	8		<ul> <li>[If DNC11 is used]</li> <li>(1) Enter the discharge start date in the western calendar format (8 digits: yyyymmdd).</li> <li>(2) Enter the time in Japanese Standard Time (JST).</li> <li>[If DNC11 is not used]</li> <li>(1) Enter the discharge start date in the western calendar format (8 digits: yyyymmdd).</li> <li>(2) Enter the time in Japanese Standard Time (JST).</li> </ul>
10	Start Time of the Discharge	С	4		[If DNC11 is used] (1) Enter the discharge start time in hour(s) and minute(s) (4 digits: hhmm). (2) Enter the time in Japanese Standard Time (JST). [If DNC11 is not used] (1) Enter the discharge start time in hour(s) and minute(s) (4 digits: hhmm). (2) Enter the time in Japanese Standard Time (JST).
11	End Date of the Discharge	М	8		[If DNC11 is used] (1) Enter the discharge end date in the western calendar format (8 digits: yyyymmdd). (2) Enter the time in Japanese Standard Time (JST). [If DNC11 is not used] (1) Enter the discharge end date in the western calendar format (8 digits: yyyymmdd). (2) Enter the time in Japanese Standard Time (JST).
12	End Time of the Discharge	С	4		<ul> <li>[If DNC11 is used]</li> <li>(1) If Start Time of the Discharge Period in "Field No. 10" is entered, the discharge end time must be entered in hour(s) and minute(s) (4 digits: hhmm).</li> <li>(2) Enter the time in Japanese Standard Time (JST).</li> <li>[If DNC11 is not used]</li> <li>(1) If the Start Time of the Discharge Period in "Field No. 10" is entered, the discharge end time must be entered in hour(s) and minute(s) (4 digits: hhmm).</li> <li>(2) Enter the time in Japanese Standard Time (JST).</li> </ul>
* [13] field	Notification Forwarding Party Code	arding Party	Code"	User Code (*)  * The code is provided by the NACCS Center in entering into an agreement for use to identify a user. Note that it differs from the Reporter ID in 4-(3) of the	[If DNC11 is used] If it is necessary to notify another user of duplicate information of Application for Cargo Discharge Permission and a notice of cargo discharge permission, enter the User Code of the user.  [If DNC11 is not used] If it is necessary to notify another user of duplicate information of Application for Cargo Discharge Permission and a notice of

Field No. (*1)	Field Name	Category (*2)	Length	Operation Code	Particulars	
				main document.	cargo discharge permission, enter the User Code of the user.	
* Fields [1	* Fields [14] "Process Identifier" and [15] "B/L Number" can be repeatedly entered up to 100 times.					
14	Process Identifier	С	1		[If DNC11 is used] If no cargo discharge permission is applied for B/L number output in "Field No. 15," enter "X" (no application). [If DNC11 is not used] No entry is required.	
15	B/L Number	М	35		[If DNC11 is used] A B/L number, for which an Advance Notice Code is registered by Japan Customs, is output. [If DNC11 is not used] Enter the B/L number, which is Master/Ocean B/L Number that has received "SPD" from Customs, in order to apply for cargo discharge permission.	

(\* 1) Field No. shows item number for corresponding Procedure Specification (input fields).

Procedure Specifications can be referred to in the Advance Filing Rules website;

(https://bbs.naccscenter.com/naccs/dfw/web/afr/index.html).

(\* 2) The following shows how to read "Category."

(1)

Category	Particulars		
M	Mandatory		
С	Conditional		
_	Mandatory if there is		
F	no complementary		
X	Entry is not available.		
-	Ignore this field.		

## (2) "Category" level

(Ex.)

Field Name	Category		
Field A	С		
Field B		М	

Lower level fields are under the category of upper level fields.

Field B is compulsory at a level lower than Field A. If Field A is entered, Field B must be entered.

(\* 3) Operation Codes are in the Advance Filing Rules web site

(https://bbs.naccscenter.com/naccs/dfw/web/afr/index.html).

<sup>\*</sup> Field A is a conditional field, which is sometimes but not always entered.